

Test Results application is a ClickOnce type of an application, meaning it's installed in user's application cache, not needing the user to specify the path. Thanks to this, the setup is a lot easier.

- Open Test Results folder>Test results Program folder
- Run setup.exe.
- Click Install.
- The application is now installed and will open right away.

How to use Adtran test Results program:

Open Start menu and run the Adtran Test Results program.

Choose what result template you would like to use by pressing the button with template name. Next to the buttons is a description what each template shows.

Once the template is chosen, a new window opens up. It has multiple buttons and settings (they depend on chosen template).


Click 'Choose Folder'. This opens a browser dialog. Navigate and choose folder that contains test results you want to process.

Test Results folder is the folder that contains the folders with names like MDS18_504VG... etc. Example of what folder to select:

Next choose what DPUs are used. Some templates allow multiple DPUs while others allow only one. At least one DPU has to be chosen (unless there aren't any)

There are multiple different settings, like FM protection, loop length or TDD value. All settings for different templates must be set, otherwise you can't proceed.

Once everything is ready, click 'START'. If everything is correct, the window will disappear and after couple seconds, an excel workbook will open. It needs some seconds to process data, but once sheets stop switching you can investigate the data displayed on different charts and in tables.



Updating Test Results program:

Open the folder containing the setup.exe and simply double click. The program will automatically update.